



RMF Install / Modify / Repair / Remove


Non-Federated Architecture (Non-Clustered Environment)

RMF Version 5.2.0

Vega Systems Inc.

03/17/2023

<https://www.vega25.com/rmf>



Setup
Non-Federated (Non-Clustered)



[Install RMF](#)



[Modify RMF](#)



[Repair RMF](#)




[Remove RMF](#)



RMF Installation Process





Installing RMF on Management Server




Step 1: Run the **RMF 5.2.0** installer on the **Management Server** (or)
Silent Install: Command Prompt → **RMF_Installer.exe /exenoui /qn INSTALL_TYPE=MS**





Step 2: Select I agree to the license terms and conditions.
Click Next.



Step 3: Click **Help (?)** to see the package description.




Step 4: Select the **Package Type - Management Server**. Click **Install**.



Step 5: Installation completed.
Click **Finish**.




Installing RMF on Smart Client Machine





Step 1: Run the **RMF 5.2.0** installer on **Smart Client Machine** (or)
Silent Install: Command Prompt → **RMF_Installer.exe /exenoui /qn INSTALL_TYPE=SC**



Step 2: Select **I agree to the license terms and conditions.**
Click **Next.**




Step 3: Select the **Package Type - Smart Client.**
Click **Install.**




Step 4: Installation completed.
Click **Finish**.




Installing RMF on Management Client Machine





Step 1: Run the **RMF 5.2.0** installer on **Management Client Machine** (or)
Silent Install: Command Prompt → **RMF_Installer.exe /exenoui /qn INSTALL_TYPE=MC**



Step 2: Select **I agree to the license terms and conditions.**
Click **Next.**




Step 3: Select the **Package Type - Management Client.**
Click **Install.**



**Step 4: Installation completed.
Click Finish.**





RMF Modify Process



RMF Modification Possibilities




Modifying RMF on Smart Client Machine





Proceed with the modification process if it is necessary to change the installed package type to another package type.

For instance, Smart Client package to Smart Client + No RMF Bookmark package.



Step 1: Run the **RMF 5.2.0** installer on **Smart Client Machine**.



Step 2: Select **Modify.**
Remove and Re-install RMF to Modify Package Type.




Step 3: Refer to [Remove RMF](#) for removing RMF.



Step 4: Refer to [Install RMF](#) to re-install RMF.

Note: Select the appropriate package type when installing RMF.




Follow the same steps to **Modify RMF on Smart Client Machine + Management Client Machine** or any other machine that has RMF installed.





RMF Repair Process





Repairing RMF on Management Server




Step 1: Run the RMF 5.2.0 installer on Management Server



Step 2: Click on the **Repair** Button.




Step 3: Click **OK** to close applications and restart after completion.




Step 4: Repair completed. Click Finish.





Repairing RMF on Smart Client Machine



Step 1: Run the **RMF 5.2.0** installer on the **Smart Client Machine**.




Step 2: Click on the **Repair** Button.




Step 3: Repair completed. Click Finish.





Repairing RMF on Management Client Machine



Step 1: Run the **RMF 5.2.0** installer on the **Management Client Machine**.



Step 2: Click on the **Repair** Button.





Step 3: Repair completed. Click Finish.




RMF Remove Process





Removing RMF from Management Server



Step 1: Run the **RMF 5.2.0** installer or Goto **Control Panel** → **Select RMF** → **Select Uninstall** option on **Management Server**.



Step 2: Click **Remove** button.



**Step 3: Removed RMF.
Click Finish.**



Follow the same steps to **Remove RMF on Smart Client Machine, Management Client Machine** or any other machine that has RMF installed.